



BLANCO COIN

Masternode Setup Guide for Windows

April 2018



Contents

1. Blanco Coin Windows Wallet Basics.....	03
1.1. How to Get the Latest Version of Windows Wallet.....	03
1.2. How to Create Your Blanco Coin Address.....	03
1.3. How to Send Blanco Coin.....	04
1.4. How to Encrypt Your Wallet.....	05
2. Masternode Setup for Windows.....	06
2.1. Getting privkey(genkey), txhash and output index.....	06
2.2. Setting up conf. file.....	08
2.3. Creating a Blanco Coin masternode.....	10



1. Blanco Coin Windows Wallet Basics


Before masternode setup, we need Blanco Coin wallet and we have to prepare our masternode address.

1.1. How to Get the Latest Version of Windows Wallet

<http://blanco-coin.com/>

1.2. How to Create Your Blanco Coin Address


Open your wallet and press “Receive” button. There you can see your default address but we need a new address for masternode so press “New Address” Button below and name your address. You will use this same name/label while creating your masternode. This is your masternode address.





1.3. How to Send Blanco Coin


Now, we need to send a specific amount of Blanco coins to our “masternode address” we have just created. Copy your masternode address and press “Send” Button. Paste it and put 5000 in amount section. We need to send exactly 5000 Blanco coins to our masternode address. You can check transaction status from “Transactions” section. We need to wait for enough confirmations to proceed.





1.4. How to Encrypt Your Wallet

You can encrypt your wallet for security but don't forget your password!






2. Blanco Coin Windows Wallet Basics

So far we have created our masternode address and sent it enough Blanco coins to run this masternode address. We have also encrypted our wallet for security. Now it's time to create our masternode. Don't worry, it is very easy!


2.1. Getting Privkey (Genkey), TxHash and Output Index

We got our masternode address ready with 5000 Blanco coins, now we need something to run our masternode. Go to "Help">"Debug Window">"Console".






Type in “masternode genkey” to get your genkey/privkey and save the result to somewhere.



Now type “masternode outputs” to get both TxHash and output index.






2.2. Setting up Conf. File

Now we need to set conf. file.

Go to C:\Users\YOUR PC NAME\AppData\Roaming\Blanco
AppData is hidden by default so you need to see hidden files. Here you can see a file named "Blanco" with the extension of "conf". Open it with notepad.



Open conf. file with Notepad

C:\Users\Your User Name\AppData\Roaming\Blanco

AppDate is hidden, u need to see hidden files.



Copy and paste these lines below in this file now, it needs to be exactly like this, 1 line at a time, also don't forget to change red phrases with yours. Save and close the file after that.

rpcuser=**Your masternode address label**

rpcpassword=**Define a password, needs to be different from rpcuser.**

rpcallowip=127.0.0.1

rpcport=25417

port=25418

listen=1

server=1

daemon=1

bind=**Your server IP**

masternode=1

externalip= **Your server IP**: 25418

masternodeprivkey=**Your masternode genkey (privkey)**



2.3. Creating a Blanco Coin Masternode

Open your wallet. Choose “Masternodes” and press “Create” button. Now you need to fill these properly. For “Alias” use the same alias/label as your masternode address. For “Address” your ip:28218 (this 28218 is our port, you may need to forward your ip if it is blocked. You can check it from port checker). You also got privkey, txhash and output index. Put them here, don’t forget “output index” is either 0 or 1. The long one is txhash. For “Reward Address” put a Blanco coin address you want masternode rewards to be sent to. You can use your masternode address. For “Reward”, type 100.

The screenshot shows the Blanco Wallet application window. The main window has a menu bar (File, Settings, Help) and a sidebar with navigation icons. The main content area is titled 'Blanco Network' and 'My Master Nodes'. A 'Create...' button is visible. Below it is a table with columns: Alias, IP/Onion, Reward %, Reward Address, and Status. An 'Add/Edit Blanco Node' dialog box is open in the foreground, containing the following fields and instructions:

- Alias*** Enter your Masternode alias. **Type in here the same name as your masternode label**
- Address*** Enter your IP & port. **Your IP:Port**
- PrivKey*** Enter your Masternode private key. **Put here the genkey/privkey you saved before (after typing "masternode genkey" at console).**
- TxHash*** Enter your 5000 BAC TXID. **Put here the txhash you saved before (after typing "masternode outputs" at console).**
- Output Index*** Enter your transaction output index. **Put here the output index you saved before (after typing "masternode outputs" at console).**
- Reward Address** Enter here Blanco Coin address you want rewards to
- Reward %** Input **Type 100 here!**

Buttons for 'OK' and 'Cancel' are at the bottom of the dialog. Below the table in the main window are buttons for 'Edit', 'Remove', 'Update', 'Start', and 'Start All'. The system tray at the bottom right shows a lock icon, a signal strength icon, a battery icon, and the text 'CLEARNET'.



Blanco - Wallet

File Settings Help

Blanco Network My Master Nodes

Create...

Alias	IP/Onion	Reward %	Reward Address	Status
-------	----------	----------	----------------	--------

Edit Remove Update

Start Start All

After creating your masternode, press "Update" button to see your masternode above.

CLEARNET

Blanco - Wallet

File Settings Help

Blanco Network My Master Nodes

Create...

Alias	IP/Onion	Reward %	Reward Address	Status
[REDACTED]	[REDACTED]	28218 100	[REDACTED]	Not in the masternode list.

Edit Remove Update

Start Start All

Now you need to press "Start" button to start your masternode. Unlock (Remove "Unlock only for staking tick") your wallet before starting if you had encrypted your wallet before.

CLEARNET



Blanco - Wallet

File Settings Help

Blanco Network My Master Nodes

Create...

Alias	IP/Onion	Reward %	Reward Address	Status
1 [redacted]	[redacted]:28218	100	[redacted]	Not in the masternode list.

Blanco-Qt

Alias: [redacted]

Successfully started masternode.

OK

Status still says "Not in the masternode list". Now press "Update" button once again to see your masternode's new status: "masternode is running"

Congratulations!

Edit Remove Update

Start Start All

CLEARNET

Blanco - Wallet

File Settings Help

Blanco Network My Master Nodes

Blanco Node Count: 3

Address	Protocol	Active	Active (secs)	Last Seen	Pubkey
1 [redacted]:28218	60025	1	00m:00s	[redacted]	[redacted]
2 [redacted]:25418	60025	1	19h:14m:09s	[redacted]	[redacted]
3 [redacted]:25418	60025	1	19h:13m:12s	[redacted]	[redacted]

CLEARNET



Blanco - Wallet

File Settings Help

You can also check if your masternode is seen in the network.

Blanco Network My Master Nodes

Blanco Node Count: 3

	Address	Protocol	Active	Active (secs)	Last Seen	Pubkey
1	[REDACTED]:28218	60025	1	00m:00s	[REDACTED]	[REDACTED]
2	[REDACTED]:25418	60025	1	19h:14m:09s	[REDACTED]	[REDACTED]
3	[REDACTED]:25418	60025	1	19h:13m:12s	[REDACTED]	[REDACTED]

Dashboard

Receive

Send

Transactions

Addresses

Masternodes

Messages

Block Explorer

CLEARNET